



## **RED CAM**

2. Go to the START menu on the bottom left of your screen, PROGRAMS and select the CEREC folder.
3. Select SERVICE.
4. You will be prompted for a password. The password is today's date (month and day reversed). For example,  
if today is September 21st, the password is 9012.
5. You will be prompted to create a new log file, select YES.
6. Select MILLING INFO.
7. Divide total milling time by 24 and you've got the number of millings.

## **BLUE CAM & Omnicam**

1. Power on your milling and acquisition unit. Verify the date on the PC is correct.
2. Go to the START menu on the bottom left of your screen, PROGRAMS and select the CEREC folder.
3. Select SERVICE.
4. You will be prompted for a password. The password is today's date (month and day reversed). For example,  
if today is September 21st, the password is 9012.
5. You will be prompted to create a new log file, select YES.
6. Select MILLING INFO.
7. Select your milling unit based on the serial number.
7. Select MACHINE DATA TYPE.
8. Look for TOTAL UNITS MILLED. This is the number of millings.

For assistance with this process, call us at (877) 237-3228.